


Sara Gómez, Universidad EAFIT.  
Jaime Humberto Hoyos, Universidad de Medellín.

---



**PLASMAPP**

# USER MANUAL

*Particle in cell simulations for electrostatic  
one-dimensional systems of plasma.*


[sgomezr3@eafit.edu.co](mailto:sgomezr3@eafit.edu.co)  
[jhhoyos@udemedellin.edu.co](mailto:jhhoyos@udemedellin.edu.co)

## WHAT IS PLASMAPP?


PlasmAPP is an App designed in MATLAB App Designer that aims to facilitate simulations of plasmas in the one-dimensional electrostatic limit using the particle-in-cell method. This App will allow you to vary the system parameters, the beam parameters, the numerical methods to solve the Poisson's equation and the equations of motion, and you will be able to choose the diagnostics you want to analyze.

## HOW TO INSTALL PLASMAPP?


- Go to the link: <https://github.com/gsara798/PLASMAPP-0.1.git>
- Download the folder "Install PlasmAPP".
- Open MATLAB and go to the "APPS" tab and then click on "Install APP".




- Go to the folder "Install PlasmAPP" and open the file "PlasmAPP".



- Click on "Install".




- Then you can run the APP.




## HOW TO SEE THE CODE OF PLASMAPP?


- Go to the link: <https://github.com/gsara798/PLASMAPP-0.1.git>
- Download the folder "PlasmAPP code".
- In MATLAB click on the tab "Open" and select the folder "PlasmAPP code" and open the files: "Start.mlapp", "Inputs.mlapp", and "Main.mlapp".



- Select the tab "Start.mlapp" and then you can run the APP.



- PlasmAPP is divided into 3 programs, each with a different graphical interface. If you wish to see the code, click on "Code View".




## PLASMAPP STRUCTURE

The implemented algorithm consists of three codes which are interconnected. Each code is described below with its graphical interface.

- **START.MLAPP**

The first program initializes the user by displaying the PlasmAPP logo. Once the logo is clicked, the Inputs.mlapp program opens. The graphical interface of this code is shown below.



## • INPUTS.MLAPP

The *Inputs.mlapp* code interface, the user enters the initial parameters needed to run the program. It has four tabs which are explained as follows:

- **System:** In this window, the user chooses the system parameters.


 The image shows the "System" tab of the PlasmAPP interface. It has a blue background and a white header bar with "File" and "Options" menus. Below the header, there are four tabs: "System", "Species", "Numerical methods", and "Diagnostics". The "System" tab is active. It contains several input fields: "Length (L)" with a value of 0, "Time step (dt)" with a value of 0, "Number of time steps (Nt)" with a value of 0, "Number of grid points (Ng)" with a value of 0, "Number of beams" with a dropdown menu showing 2, and "Steps for plots" with a value of 0.

- **Species:** Once the user chooses the number of beams to simulate in the System window, the characteristics of each species can be determined in the Species tab.


 The image shows the "Species" tab of the PlasmAPP interface. It has a blue background and a white header bar with "File" and "Options" menus. Below the header, there are four tabs: "System", "Species", "Numerical methods", and "Diagnostics". The "Species" tab is active. It contains several input fields: "Number of beams" with a dropdown menu showing 2, "Electrons" with a radio button selected, "Specie 2" with a radio button unselected, "Number of ions in background (Ni)" with a value of 0, "Density (N1)" with a value of 0, "Mean Velocity (V01)" with a value of 0, "Thermal Velocity (Vth1)" with a value of 0, "Charge mass relation (QM1)" with a value of 0, "Perturbation amplitude (XP1)" with a value of 0, "Mode 1 (M1)" with a value of 0, and "Plasma frequency (WP)" with a value of 0.

If you want to use the background ions, it is important to put the same number of electrons and ions.


- **Numerical methods:** In this tab the numerical methods for solving the equations of motion and Poisson's equation are chosen.



- **Diagnostics:** In the last tab, the user selects the diagnostics to be observed.




Additionally, the user has the option to export data in text format, import data in the same format, and can load the selected examples by clicking on the file button in the menu. Once the user presses the button to run the program, all variables are saved in a data vector. Subsequently, the Main.mlapp program is opened and this vector is sent to it.



## • MAIN.MLAPP

The last code is used to process the variables and with these to implement the PIC algorithm, additionally, in the graphical interface the diagnostics selected by the user must be observed. The interface contains a tab for each diagnostic chosen by the user and a last tab that collects all the diagnostics. The user is able to edit the title of the graph and the labels, limits, and ticks of the axis. In addition, the user can observe the simulations in the iterations available in the slider. Finally, in the last tab, you can see the maximum error percentage for energy, the maximum error percentage for momentum, and the execution time.



In order to post-process the simulation, the results of the variables can be saved by clicking on "file" and then on "Save variables .mat".

